









Block – Decorative Stitching / Mirage



Fabric	Colour	Size (inches)	Preparation
Background	Black	8 ½ x 8 ½	
Stabiliser		8 ½ x 8 ½	Tear away
Notes:			

Needle Plate: Standard 	Foot: Satin Stitch F2 	Thread: Teal 	Needle: Janome Sharp 12 
Stitch: Decorative Stitches 	> Heirloom 	> Stitch 39 	




1. Line up the edge of the fabric near the edge of the foot




2. Stitch across the block




3. Line up the foot with the previous row of stitches




4. Select stitch H40




Sew across the block



5. Select stitch Q49



Sew across the block



6. Continue to sew different stitches to fill the block. Trim block to 8" square.









Block – Shell Tuck / Professional Plate & Foot




Fabric	Colour	Size (inches)	Preparation
Background	Green	8 ½ x 8 ½	
Fabric	Black	8 x 8	Cut into two HST
Shell Tuck	Red	1 x 20	Press in half lengthwise
Binding	Button	2 ½ x 20	Press in half lengthwise


Notes:

Shell Tuck


Needle Plate: Standard 	Foot: Satin Stitch F 	Thread: White 	Needle: Janome Blue Tip 
Stitch: Sewing Applications 	> Sewing Tab 	> Shell Tuck 	> Large 




1. Fold fabric strip in half lengthwise



2. Line the folded edge of the white fabric strip with the split in the F foot so that the needle clears the fabric on the right-hand side



3. Sew along the length of the strip




4. Cut in half and place one piece on either side of the corner of quilt wadding, raw edges together
Glue baste in place




5. Change the needle plate
Press the Lockout key



6. Press needle plate release key, the foot and needle plate will raise automatically







7. Remove the plate to the right




8. Replace with the HP Professional plate

Professional Binding

<p>Needle Plate: HP Professional</p> 	<p>Foot: HP2 Professional AcuFeed Flex foot</p> 	<p>Thread: White</p> 	<p>Needle: Janome Red Tip</p> 
<p>Stitch: Utility U1</p> 			
<p>Settings: Press Foot Up Key (Pivot)</p> 		<p>Press Dual Feed Key (Acufeed)</p> 	



1. Place the start of the binding strip over the shell tuck pieces
Line up all the raw edges to the edge of foot
Start to sew ¼" seam allowance




2. STOP ¼" before the end of the quilt corner, use the markings on the foot and needle plate as guides



3. Rotate quilt 45° clockwise




4. Stitch out towards the corner point




5. Cut threads




6. Fold the binding up against the diagonal stitch line



7. Then fold it straight down towards the second side, lining up the raw edges



8. Sew from the edge of the fabric




9. Finger press the binding out over the edge of the quilt and around to the back



10. On the front, pin along the ditch between the shell tuck and binding to hold in place



11. Stitch in the ditch to secure the binding in place



12. Pivot the quilt at the corner



13. Stitch to the end of the binding



14. Centre onto the pink backing square



15. Stitch along the top edge 2-3mm from the raw edges. Trim block to 8" square.